


{A Ms. Cleaver Creation}

Cargo/Bellows Pocket Instructions: (Adapted from 21wale.com)

1. Cut out pockets and flap
2. Finish edges of pocket (not notches)
3. Fold down top of pocket to meet fold line, then fold under at fold line. Press and top-stitch hem
4. Sew soft side of Velcro on outside/right side of pocket in center of top hem.
5. Fold all dashed lines toward wrong side and press.
6. Accordion fold all dotted lines in toward center and press.
7. Pinch the corner to form box shape and stitch along corner stitching line. Check corner is sewn properly into box shape and trim excess. Repeat for other corner.
8. Edgestitch the sides and bottom of the face of the pocket, using three straight lines of stitching, making sure to not catch the seam allowance or bellows.
9. Push in accordion folds and re-press as needed.
10. Pin pocket on garment, with seam allowance on the inside, making sure the bellows are directly below the face of the pocket. Use lots of pins to keep them in place, if needed.
11. Edgestitch the lower edge of the bellows to the garment.
12. With wrong sides together, fold flap along fold line and sew sides with 5/8" seam. Turn right side out and press. Zig-zag raw edge of pocket together.
13. Edgestitch flap sides and bottom.
14. Fold and press pocket flap 5/8" from zig-zag edge.
15. Line up zig-zag edge of flap with top of pocket. Mark Velcro placement and sew hook side of Velcro to inside of flap.
16. Line up zig-zag edge of flap with top of pocket and stitch to garment along seam allowance fold line.


Pocket Template and Instructions provided by MsCleaver.com




FOLD LINE


Cargo Pocket for
Minoru Jacket by
Sewaholic Patterns

SEAM AI



Pocket Template
by
MsClever.com





1 INCH
SQUARE

{A Ms. Cleaver Creation}

CORNER
STITCHING
LINE

